

Version History

Razor PDM Firmware
PDMLink Software



Release 2

Software Version	1.2.72
Firmware Version	1.2.28
Release Date	15/09/2022

PDMLink

- General updates. Regenerated User Manual, Removed redundant files from installer, changed default app logging level to provide better feedback, Added high DPI monitor and Windows 11 support.
 - Issues #145, #148, #130, #128, #123
- Fixed issues with offline configuration by adding default PDM data. Improves a range of behaviors such as inability to perform offline configuration, enumerated values showing as numbers, and issues loading config files prior to PDM connection.
 - Issues #144, #146, #147, #118
- Minor UI adjustments – corrects some icon sizes.
 - Issue #137
- Fixed crash bugs – when User Manual was previously open, and when loading config files from a fresh install.
 - Issues #121, #129
- Added a Tools menu item to remove cached PDM data – requires restart.
Used to refresh PDM data – this is required by pre release testers but may be useful for general users.
This does not delete user data.
 - Issue #118

Razor PDM Firmware

- Improved Math and logic expressions.
 - Adds new operators: =, ==, !=, >=, <=, ^ (xor).
 - Adds new functions: int(), pow(), if()
 - Issue #5

Release 1

Software Version	1.1.65
Firmware Version	1.1.15
Release Date	02/09/2022

PDMLink

First release

Razor PDM Firmware

First release

Revision History

Version	1.2.72	15/09/2022
	1.1.65	02/09/2022